


Installation Steps for an SR140 FoIP FAXCOM Solution*


1



Either insert the FAXCOM Server CD, or unzip the BDS package, and run setup.exe to install the software, selecting SR140 Virtual Board (T38) as the fax board type.

FAXCOM Fax Server


2



On the FAXCOM Fax Server, select **Configure...All Settings...SR140 Settings**. Click the License Manager button to display the Brooktrout License Manager.

FAXCOM Fax Server


3



Select **Utilities...Display Node Lock** and obtain the Node Lock Type and Node Lock.

FAXCOM Fax Server


4



Select **License...Activate License** to display the License Activation Wizard Welcome screen and click Next.

FAXCOM Fax Server

5



When the Activation Method screen is displayed, select the **Using the interactive Web method** and click Next. When the Web Instructions screen is displayed, click the Save the instructions into a file button and click Save. Click Next; click Finish; exit the utility.

FAXCOM Fax Server


6

From any system on your network, run a Web browser and access: <http://www.dialogic.com/activation>. Enter your License Key from the SR140 Certificate and click Submit. Enter Customer Information and click Submit. Click the Generate Licenses button.

7

Select the appropriate Node Lock Type in the Node ID Type field and enter the Node Lock in the Node ID field. When prompted, click Confirm. Click the Save to File button on the Deliver License page. Click Logout.

8




On the FAXCOM Fax Server, place the license information file in the appropriate directory, either:

- `drive\Program Files\Biscom\FAXCOM Server\Cantata SR140`
- or
- `drive\Program Files (x86)\Biscom\FAXCOM Server\Cantata SR140`.

FAXCOM Fax Server

9




Either insert the FAXCOM Suite for Windows CD, or unzip the BDS package, and run Setup.exe.

FAXCOM Queue Server

* Note: When implementing SR140 on a virtual machine, make sure to assign the MAC address manually instead of allowing VMware Workstation to assign it automatically.

FAXCOM Solution Architecture



- For an installation roadmap, see reverse.
- For complete information on the FAXCOM Fax Server, see *FAXCOM Servers Administrator's Guide.PDF* in the Documentation folder of the FAXCOM Server CD, or access the online help within the FAXCOM Server Administrator program.
- For complete information on FAXCOM Suite for Windows, see *FAXCOM Suite for Windows Administrator's Guide.PDF* in the Documentation folder of the FAXCOM Suite for Windows CD, or access the online help within the FAXCOM Suite for Windows Administrator program.