


Cisco Collaboration – Cisco Unity Connection Localization

下面的详细步骤是如何安装本地化的功能和语言到 Cisco Unity Connection for the Cisco Collaboration 的演示。

下载 Unity Connection Locale 文件

1. 在 **Workstation 1 desktop**, 打开一个网页浏览器到 <http://www.cisco.com/>并点击在网页底部的 Support 区的 **Downloads** 连接。
2. 使用页面中间的导航窗格, 点击 **Downloads Home > Products > Unified Communications > Unified Communications Applications > Messaging > Cisco Unity Connection > Cisco Unity Connection Version x.x (example 10.5)**.
3. 点击 **Unity Connection Locale installer xx**, 其中 **xx** 是您需要的语言。将文件保存到 **Workstation 1 desktop**. 您必须使用 Cisco 授权的 ID 来执行 **Login** 这个操作。

Figure 1. 导航窗格



停止服务器并加载本地文件

1. 在 Workstation 1 的桌面打开一个网页浏览器, 然后导航到 Cisco dCloud 主页上 <http://ad1.dcloud.cisco.com/dCloud/default.html>
2. 点击 **Collaboration Admin Links > Cisco Unity Connection Admin**.
3. 以 **administrator** 身份登录, 密码 **C1sco12345**.
4. 在右边顶端的 **Navigation** 下拉, 选择 **Cisco Unity Connection Serviceability** 并点击 **Go**.
5. 停止以下服务器, 并点击两个服务器的 **Tools > Service Management > Click Stop**。点击 **OK** 继续。
 - a. Connection Conversation Manager
 - b. Connection Mixer

Figure 2. 服务器管理

The screenshot displays the Cisco Unity Connection Serviceability web interface. The navigation menu is open, showing options like 'Cluster Management', 'Service Management', 'Reports', and 'Voice Network Map'. The 'Service Management' option is circled in red. Below the menu, there are three tables of services:

Service Name	Running Time	Activate Status	Service Status
Connection DB	97:30:03	Activated	Started
Connection License Manager Server	97:29:31	Activated	Started
Connection Server Role Manager	97:29:33	Activated	Started
Connection Serviceability	97:08:30	Activated	Started

Service Name	Running Time	Activate Status	Service Status	Change Service Status
Connection Conversation Manager	97:21:49	Activated	Started	Stop
Connection Mailbox Sync	97:20:27	Activated	Started	Stop
Connection Message Transfer Agent	97:21:49	Activated	Started	Stop
Connection Mixer	97:21:49	Activated	Started	Stop
Connection Notifier	97:21:49	Activated	Started	Stop

Service Name	Running Time	Activate Status	Service Status	Change Service Status
Connection Administration	97:08:30	Activated	Started	Stop
Connection DB Event Publisher	97:29:34	Activated	Started	Stop


6. 在 Workstation 1 桌面，点击 **Windows Start icon > All Programs > FreeFTPd > FreeFTPd**.
7. FreeFTPd 打开，点击 **FTP > Start**.
8. 在 **Cisco Unity Connection** 网页上，点击 **Navigation** 下拉，并选择 **Cisco Unified OS Administration**，然后再点击 **Go**。以 **administrator** 身份登录，密码是 **C1sco12345**。
9. 点击 **Software Upgrades** 并选择 **Install/Upgrade**。
10. 输入以下信息并点击 **Next**.
 - a. Source: Remote File System
 - b. Directory: /
 - c. Server: 198.18.1.36
 - d. Username: demo
 - e. Password: C1sco12345
 - f. Transport Protocol: FTP

11. 在接下来的页面中，选择您下载的语言环境， 点击 **Next**，然后在点击 **Install**。

重启服务器并选择系统区域设置

1. 从右上角的 **Navigation** 下拉并选择 **Cisco Unity Connection Serviceability** 并点击 **Go**。
2. 以 **administrator** 身份登录并 **C1sco12345**。
3. 启动以下的服务器，通过单击两个服务器的 **Tools > Service Management > Click Start**
 - a. Connection Conversation Manager
 - b. Connection Mixer
4. 在 **Workstation1 desktop**，双击 **putty.exe**。点击 **Run** 继续。
5. 点击 **SSH** 并输入 Unity Connection Server 的 IP 地址， **198.18.133.5**。
6. 点击 **Open** 然后 **Yes** 继续。
7. 以 **administrator** 身份登录，密码是 **C1sco12345**。
8. 通过输入“**utils service restart Cisco Tomcat**”，然后按 **Enter** 键，重启 Tomcat 服务器。输出应与下图一致。

Figure 3. 通过命令行停止 Cisco Tomcat 服务器



```

198.18.133.5 - PuTTY

Welcome to the Platform Command Line Interface

VMware Installation:
 1 vCPU: Intel(R) Xeon(R) CPU E7- 2830 @ 2.13GHz
 Disk 1: 160GB, Partitions aligned
 4096 Mbytes RAM


admin:
admin:utils service restart Cisco Tomcat
 Don't press Ctrl-c while the service is getting RESTARTED.If Service has not Re
started Properly, execute the same Command Again
Service Manager is running
Cisco Tomcat[STOPPING]
Cisco Tomcat[STOPPING]
Cisco Tomcat[STOPPING]
Cisco Tomcat[STOPPING]
Cisco Tomcat[STARTING]
Cisco Tomcat[STARTING]
Cisco Tomcat[STARTING]
Cisco Tomcat[STARTING]
Cisco Tomcat[STARTED]
admin:

```

9. 点击 **Navigation** 下拉并选择 **Cisco Unity Connection Administration** 并点击 **Go**。
10. 点击 **System Settings > General Configuration > System Default Language**。

11. 选择您想要使用的语言并点击 **Save**.

Figure 4. 选择系统默认语言



Unity Connection 本地化指南到此结束。



Americas Headquarters
Cisco Systems, Inc.
San Jose, CA

Asia Pacific Headquarters
Cisco Systems (USA) Pte. Ltd.
Singapore

Europe Headquarters
Cisco Systems International BV Amsterdam,
The Netherlands

Cisco has more than 200 offices worldwide. Addresses, phone numbers, and fax numbers are listed on the Cisco Website at www.cisco.com/go/offices.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)