

router bgp AAAAA
bgp log-neighbor-changes
network 12.y.y.16 mask 255.255.255.248
network 170.x.254.0 mask 255.255.255.0
neighbor 12.x.x.9 remote-as ZZZZ
neighbor 12.x.x.9 default-originate

interface GigabitEthernet0/0/5
ip address 170.x.254.3 255.255.255.0
standby 1 ip 170.x.254.1
standby 1 priority 105
standby 1 preempt
standby 1 track 1 decrement 10
standby 2 ip 170.27.254.2
standby 2 priority 100
standby 2 preempt
standby 2 track 2 decrement 10
speed 1000
no negotiation auto

router bgp AAAAA
bgp log-neighbor-changes
network 170.x.254.0 mask 255.255.255.0
neighbor 50.x.x.81 remote-as YYYY

interface GigabitEthernet0/0/5
ip address 170.x.254.4 255.255.255.0
standby 1 ip 170.x.254.1
standby 1 priority 100
standby 1 preempt
standby 1 track 1 decrement 10
standby 2 ip 170.x.254.2
standby 2 priority 105
standby 2 preempt
standby 2 track 2 decrement 10
speed 1000
no negotiation auto