

Sourcefire to Cisco - Licensing Delta Guide

Licensing Delta Guide

Welcome to the Sourcefire to Cisco Licensing Delta Quick Guide. This document provides a short summary of the differences between the Sourcefire Licensing portal capabilities and the Cisco License Registration Portal (LRP) capabilities.

For additional instructions and 'how-to' videos for the Cisco License Registration portal, please refer to the flash landing page upon logging in.

Recommendations/Guidelines

- Recommended Browsers: Google Chrome, Mozilla Firefox
- Have your Cisco Connection Online (CCO) ID & Password available
 - o Don't have an account? Please click here to Create a New Account.
- Visit the Sourcefire License Support Forum for additional helpful information and discussions.

Key Highlights

- Cisco LRP provides many self-serve functionalities
- Cisco LRP allows users to create their own accounts
- Discussion Forums are available for various types of inquiries

Table of Contents

Summary of Sourcefire to Cisco Capabilities

Sourcefire License Portal vs. Cisco License Registration Portal

- LRP Landing Page
- License Request Form
- License Entitlements Page
- Software Downloads

Cisco Node Lock Process

- Version 5.1 or above Software
- Version 4.10 Software


Summary of Sourcefire to Cisco Capabilities

Discussion Forum: Sourcefire Cisco Support Community

Capabilities	Sourcefire	Cisco	Description
Registration	Keyserver.sourcefire .com	Create an Account: https://sso.cisco.com/autho/forms/C DClogin.html	How users would register to have the ability to use licensing features
License Share	Support Call	Self-Serve Function	Applying the same license on multiple Defense Centers/Devices
Add License	Support Call	Self-Serve Function	Adding a license using an existing PAK
Return Materials Authorization (RMA)	Support Call	Self-Serve Function	Returning a product after purchase
License Copy	Support Call	Self-Serve Function	Duplicating a license to apply it to another Defense Center/Device
Resend	Support Call	Self-Serve Function	Request to send a copy of an existing license
Access	NA	CCO ID & Password	Entering the portal to complete various licensing functionalities
Node Lock	License Key	License Key	Defense Center ID/Device ID number
Proof of Entitlement	Activation Key	Product Authorization Key (PAK)	The key provided to the end user to generate/add a new license
Activation Tools	Keyserver.sourcefire .com	Cisco License Registration Portal (LRP) (aka Software Infrastructure Fulfillment Technology (SWIFT)) - www.cisco.com/go/license	Tool used to complete licensing functionalities
Support Case	Support Call	Global License Operations (GLO) & Discussion Forums: https://supportforums.cisco.com/community/12186751/license	End users would contact specific groups for support


Sourcefire License Portal vs Cisco License Registration Portal

Sourcefire to Cisco Licensing Registration Portal Landing Page



Before:


Sourcefire Licensing Landing Page: This page appears when clicking the 'Licensing' Tab with instructions on requesting product licenses.



Cisco Licensing Landing Page: This page appears upon logging into the license tool. Users are able to view helpful guides and 'how-to' videos on this page. Clicking the green 'Continue to Product License Registration' button will navigate users to the licensing main page.




Sourcefire to Cisco License Request Form




Before:

Sourcefire License Request Form: Users would complete this form every time they need to request a license.



Cisco Licensing Request Page: Users are able to complete various licensing functionalities from the main page (please see the summary table above and the flash landing page for more information)




Before Tools A Resources Product License Registration | Very in Product | Control | 1/2 | Feebback | Note | Control | 1/2 | Feebback | Note


Sourcefire to Cisco License Entitlements Page

Before:

Sourcefire Entitlements Page: Users would view the 'Entitlements' tab to look up their entitlements, which will show all records.




Cisco License Registration Portal 'Entitlements' Page: The entitlements can be viewed by clicking the 4 different tabs under the Manage section from the main page. View by PAKs, Licenses, Devices, or Transaction History.




Back to Table of Contents

Sourcefire to Cisco Downloads Page



Before:


Sourcefire Downloads Page: Users may be entitled through their licenses to patches, upgrades and other content available via the Downloads tab. If available, a hierarchical list of downloads will appear. Software can be downloaded and applied to devices, as well as, retrieve licenses needed for devices here on this tab.



Cisco Download Page: Software download for the Sourcefire products are available for FirePOWER and FireSight.


FirePOWER Software Download Page:

 $\frac{\text{http://software.cisco.com/download/release.html?i=!y\&mdfid=286261236\&softwareid=286271056\&release.html?i=!y\&mdfid=286261236\&softwareid=28626261236\&softwareid=28626261236\&softwareid=28626261236\&softwareid=28626261236\&softwareid=2862626261236\&s$



FireSight Software Download Page:

 $\frac{\text{http://software.cisco.com/download/release.html?mdfid=286261232\&flowid=54049\&softwareid=28627105}{6\&release=5.2.0.5\&relind=AVAILABLE\&rellifecycle=\&reltype=latest}$



Node Lock Process


Identifying License key of the Defense Center (For Version 5.1 and above Software)

In Sourcefire, all the licenses reside on the Defense center. License key of the Defense center which is combination of Model_number + Mac_ID of the Defense center is the NODE lock information.

Users can get the license key information on the Defense center by following below steps,

Steps:


- 1. Login to Defense center with Admin privileges
- 2. Select System -> Licenses, License page will appear
- 3. Click on "Add new License". The "Add Feature License" page will appear
- 4. License Key of the Defense center will be displayed




License Key of the Defense center must be provided to register a PAK (Authentication Key).

Adding a License to the Defense Center (For Version 4.10 Software)

- 1. Login to Defense center with Admin privileges
- 2. Select **Operations -> System Settings**, Information page will appear.
- 3. Click on "License". The "License" page will appear.



- 4. Click "Add New License". The "Add License" page appears.
- 5. License Key of the Defense center will be displayed



Back to Table of Contents

Thank you!